

TEMPRA VISION INSTALLATION INSTRUCTIONS

Welcome to TEMPRA Vision — the multimedia product that will take you into the 21st Century! **BE SURE TO SEND IN YOUR REGISTRATION CARD TO RECEIVE SIX MONTHS TOLL-FREE TECHNICAL SUPPORT.** To install the complete TEMPRA Vision program, follow the instructions carefully. We want you to have lots of fun with TEMPRA Vision. If you have any problems installing the program, please do not hesitate to call us at 1-800-852-6484. A technical support representative will walk you through the installation procedure step-by-step.

1. Put the TEMPRA MEDIA CD-ROM in the CD-ROM drive.
2. Put the TEMPRA Special Edition disk that came with TEMPRA Vision in the floppy disk drive and type A:INSTALL or B:INSTALL and press [Enter]. Follow the instructions on the computer screen.
3. The default drive for installing TEMPRA Vision is drive C. If you want to install TEMPRA Vision on a hard drive other than drive C, use your cursor keys to move the flashing cursor to select the drive you want, then press the [Enter] key. TEMPRA Vision installs into the \VISION directory without giving you an option to change it.
4. The installation program checks to see if you have enough space on your hard drive to install TEMPRA Vision (TEMPRA Vision requires 35Mb). If 35Mb is available, all TEMPRA Vision files are installed on your hard drive in the directory \VISION. If you don't have enough disk space, you can select a story from the story module to be copied onto your hard drive.
5. Use the cursor keys to move the flashing bar to highlight the story you want to install and then press the [Enter] key. The files for the story you select are copied to the hard drive into the \VISION directory.
6. To start the stories from the C:\VISION> prompt, type the appropriate command shown below:

VISDEMO (a self-running version of the entire story module)
STORY (an interactive version of the entire story module)
DAYFARM (A Day on the Farm)
UGBUZZ (Ugh and Buzz)
BUZZVAC (Buzz Takes a Vacation)
PPLAY (Paint and Play)

NOTE: The first time you use Paint and Play or TEMPRA GIF, you need to configure the VGA card in your computer. The Configuration menu comes up automatically, and you just choose the card. If you don't know the name of your card, select "SuperVGA 256 Colors."

Installing TEMPRA Special Edition from the Book "Multimedia: Making It Work"

If you have the book "Multimedia: Making It Work," it includes a 24-bit TEMPRA Special Edition that allows you to edit images in up to 16.7 million colors. If you want to use the TEMPRA Special Edition that came with the book, follow these instructions:

1. Put the TEMPRA MEDIA CD-ROM in the CD-ROM drive.
2. Put the TEMPRA Special Edition disk that came in the TEMPRA Vision box in the floppy disk drive and type A:INSTALL2 or B:INSTALL2 and press [Enter]. Follow the instructions on the computer screen.
3. The default drive is drive C. If you want to install TEMPRA Vision on a hard drive other than drive C, use your cursor keys to move the flashing cursor to select the drive you want, then press the [Enter] key.
4. The default directory is C:\TEMPRA. When the program asks if you want to change the directory, use your backspace key to erase \TEMPRA and then type \VISION and press the [Enter] key.
5. After you install the TEMPRA Special Edition from the book, you need to copy some files from the CD-ROM into the C:\VISION directory for the story module to work properly. To make sure you are in the right directory, type CD\VISION and press the [Enter] key. Make sure that the TEMPRA MEDIA CD is still in the CD-ROM drive.
 Type COPY D:\VISION*.RDS and press the [Enter] key.
 Type COPY D:\VISION*.INF and press the [Enter] key.
 Type COPY D:\VISION*.CFG and press the [Enter] key.
 Type COPY D:\VISION*.PTH and press the [Enter] key.

TEMPRA MEDIA CD-ROM INSTALLATION INSTRUCTIONS

In addition to the TEMPRA Vision story module, this CD-ROM includes the following demonstrations and programs:

TEMPRA Access Software for loading, manipulating, and saving Photo CD images. (Requires 4Mb disk space.)

CD-ROM directory: D:\ACCESS
 Hard disk directory: C:\TEMPRA
 Command line: ACCESS

TEMPRA PRO Fully functional TEMPRA PRO software to explore TEMPRA's image editing capabilities. No save, print, and scan. (Requires 8Mb disk space.)

CD-ROM directory: D:\PRIMER
 Hard disk directory: C:\PRIMER
 Command line: TEMPRA

MADemo Interactive demonstration using TEMPRA Media Author program with animation, audio, graphics. Great for in-store demos! (Requires hi-color VGA card and 90Mb disk space.)

CD-ROM directory: D:\MADemo
 Hard disk directory: C:\MADemo
 Command line: MADemo Exit command: Ctrl-C

USERDEMO Interactive presentation highlighting the complete TEMPRA product line. Great for in-store demos! (Requires superVGA or hi-color card and 16Mb disk space.)

CD-ROM directory: D:\USERDEMO

Hard disk directory: C:\USERDEMO

Command line: USERDEMO

Exit command: Ctrl-C

PROSONUS MusicBytes music and sound effects library from Prosonus. Audio files are in VOC, WAV, and MIDI formats in 5, 15, 30, and 60 second versions. The installation puts only the 5-second VOC files onto the hard drive. To load other audio files onto your hard drive, simply copy them from the CD-ROM into the desired directory. (Requires Sound Blaster compatible audio card and 11Mb disk space.)

CD-ROM directory: D:\PROSONUS

Hard disk directory: C:\VISION\AUD

Command line: none

You can run these programs and demos from the CD, but the speed won't be as fast as it should be. If you have the disk space, we recommend installing the programs on your hard drive to use them. You can install any of the programs or demos at any time by repeating the installation instructions below. All programs and demos install to default directories. If you don't have enough disk space, the install program aborts.

To install the TEMPRA PRO primer, the TEMPRA Access program, the MADEMO or USERDEMO sequences, follow these instructions:

1. Insert the TEMPRA MEDIA CD in the CD-ROM directory (probably D:\) and type install.
2. The "Welcome to the TEMPRA MEDIA CD" screen pops up.
3. Continue reading the information until you see the screen: "Which of the following programs would you like to install?"
4. You can choose either to load TEMPRA Access or move the highlight bar to one of the following:

**TEMPRA Vision (VISDEMO IS A SELF-RUNNING DEMO THAT CAN BE
COPIED FROM THE CD TO YOUR HARD DRIVE)**

PROSONUS Music and Sound Effects

In-store TEMPRA Demonstrations

(You can only load one program or demonstration at a time, so just repeat this procedure when you are ready to install another program or demo.)

5. If you choose In-store TEMPRA Demonstrations, you'll see:

TEMPRA PRQ Primer

TEMPRA MADEMO

TEMPRA USERDEMO

6. Choose the demonstration you want to load and follow the installation instructions.

TEMPRA ACCESS

If you want to use a Kodak Photo CD to make stories using pictures of your family that are stored on CD-ROM you will definitely want TEMPRA Access on your computer. This CD contains 24 Kodak Photo CD images you can load using TEMPRA Access. You can then save the images to hard disk in any file format available to use in stories and graphics. TEMPRA Access is a 24-bit program that takes advantage of the photographic quality of the images stored on the CD-ROM. If you are using the 8-bit TEMPRA Special Edition, the Photo CD images won't look as good as they will on a hi-color VGA board. If 24-bit capability is important to you, we recommend you use the 24-bit Special Edition that came with the book "Multimedia: Making It Work" or that you upgrade to TEMPRA PRO.

To load images from Photo CD:

1. In TEMPRA Access, move the cursor to the DSK menu and press the left mouse button
2. Select Photo CD from the drop-down menu.
3. A contact sheet appears on the screen showing miniatures of all the images on the CD.
4. Select an image to load.
5. A menu appears for you to select the size you want the image to be. Select the size you want and press the left mouse button.
6. The image loads onto the screen in the selected size.

To save images onto disk:

1. Once the image is loaded on the screen, you can save it in any of the available file formats.
2. Move the cursor to the DSK menu and press the left mouse button.
3. Select Files from the drop-down menu.
4. Make sure the Images button is highlighted and that you are in the C:\VISIONPIC directory (or another directory you want to save your images in).
5. Select the file format you want to save the image as. If you are using the 8-bit TEMPRA GIF, you will want to save your image in 8-bit so you can edit it later. If you have a 24-bit TEMPRA GIF, you can save the image in either 8-bit, 16-bit, or 24-bit and edit it later in TEMPRA GIF. If you know you will use the image in TEMPRA SHOW for a story or presentation, make sure you save the file as either 8-bit PCX or 16-bit TGA.
6. Move the cursor to the box above the list of files in the directory and press the left mouse button. The box changes color.
7. Type the name you want to give the picture.
8. Move the cursor to the Save button and press the left mouse button. The menus disappear while the image is being saved. When the menus come back, your image has been saved on the disk in the new file format.

NOTE: The Blast_Buf has been set in the autoexec.bat file to 15. This should satisfy most computers in allowing audio and image files to run smoothly simultaneously. If you notice a choppiness or any cutting up of audio files, you may need to increase the Blast_Buf.

REMEMBER: Call 1-800-852-6484 if you would like help installing TEMPRA ACCESS.